



ZOOM AUDIO SETTINGS FOR HARMONICA


1. Click the Settings Cog



2. The Setting Window Will pop up



3. Select Audio – Untick the microphone volume box indicated, and set your volume slide to about 60%. Now click the Advanced button.



The screenshot shows the Zoom Settings window with the 'Audio' tab selected. The 'Speaker' section is visible, showing 'Speakers (2- Realtek(R) Audio)' selected and the 'Volume' slider set to approximately 60%. The 'Microphone' section shows 'Microphone (Yeti Stereo Microphone)' selected and the 'Volume' slider set to approximately 60%. The checkbox 'Automatically adjust microphone volume' is unchecked. The 'Advanced' button is located at the bottom right of the settings panel. Red arrows point to the 'Audio' tab, the 'Automatically adjust microphone volume' checkbox, the microphone volume slider, and the 'Advanced' button.

Settings

- General
- Video
- Audio**
- Share Screen
- Chat
- Background & Filters
- Recording
- Profile
- Statistics
- Feedback
- Keyboard Shortcuts
- Accessibility

Speaker

Test Speaker Speakers (2- Realtek(R) Audio)

Output Level: _____

Volume: _____

Use separate audio device to play ringtone simultaneously

Microphone

Test Mic Microphone (Yeti Stereo Microphone)

Input Level: _____

Volume: _____

Automatically adjust microphone volume

Suppress background noise Auto ?

Select the default noise suppression level (low) to optimize for music

Automatically join audio by computer when joining a meeting

Mute my microphone when joining a meeting


Do not prompt the join audio dialog when I am using third party audio

Press and hold SPACE key to temporarily unmute yourself

Sync buttons on headset

Advanced

4. Set Echo Cancellation to Auto. Tick the 'Enable Original Sound' box – this is really important! Leave the remaining boxes unticked.



The screenshot shows the Zoom Settings window with the 'Audio' tab selected and the 'Advanced' options expanded. The 'Echo cancellation' dropdown is set to 'Auto'. The checkbox 'Show in-meeting option to "Enable Original Sound" from microphone' is checked. The 'When original sound is enabled' section has three options: 'Disable echo cancellation', 'High fidelity music mode', and 'Use stereo audio', all of which are unchecked. Red arrows point to the 'Echo cancellation' dropdown, the 'Show in-meeting option...' checkbox, and the 'Disable echo cancellation' option.

Settings

- General
- Video
- Audio**
- Share Screen
- Chat
- Background & Filters
- Recording
- Profile
- Statistics
- Feedback
- Keyboard Shortcuts
- Accessibility

< Back

Echo cancellation Auto

Show in-meeting option to "Enable Original Sound" from microphone ?


When original sound is enabled

Disable echo cancellation ?

High fidelity music mode ?

Use stereo audio ?

5. When you join your next meeting, you will see a blue button that reads 'Turn off Original Sound'. Don't change this. It means your Original Sound setting has been activated and your PC won't mute you when you play harmonica. If you need to readjust the Audio settings during your meeting, use the Mute icon indicated at the bottom of the screen.



6. The Audio menu will pop up. Here you can check the microphone and speakers Zoom has selected, and run a quick test. You can also fast track back to the Audio Settings screen shown in item 3 above.

